

AnnotAR Interaction Steps

Enter Annotation mode



In order to enter annotation mode, click the *Annotation* button.

1. Insert an annotation

1.1) Highlight text



To highlight text, click the *Highlight* button. Then, long press on a specific word on text and then expand the selection.

1.2) Add a marker to a map



Click the *Marker* button. Then, click on the specific point on the map where you want to insert the marker.

1.3) Select interval in a video



Click the *Interval* button.




Then, navigate to the desired start time in the video, and click the *Confirm* button under text *Select Start point for Annotation Interval*.



Lastly, navigate to the desired end time in the video, and click the *Confirm* button under text *Select End point for Annotation Interval*.

1.4a) Draw a shape on text or on video



Click the *Drawing* button. Then, slide your finger on screen to directly draw on text or video.

1.4b) Draw a shape on a map




Click the *Drawing* button. Then, click successive points on the map to draw a shape that connects these points.

2. Create Annotation content

2.1) Take a photo with the Headset



Click the *Headset* button.




On the Menu that pops up in the air, click the *Take Picture* button. Wait for confirmation.

2.2) Take a video with the Headset



Click the *Headset* button.



On the Menu that pops up in the air, click the *Start Recording* button.




When you want to stop recording, click the *Stop Recording* button.

2.3) Add a picture from the handheld device



Click the *Handheld Device* button.



Select the *Photo Library* option. Choose the picture, click on it, and click *Use*.

2.4) Add a Post-It Note



Click the *Post-It Note* Button.



Draw on the Post-It Note that pops up on the handheld device. If you want to type text, click the *Text* button on the top right and start typing with the keyboard.

Click the *Confirm* button at the bottom right when you are done.